Table of Contents

MagicPlot User Guide	
System Requirements and First Launch	1
Getting Started: Tables, Figures, Fit Plots and Undo	2
Importing Table from Text File (ASCII)	3
Table Editing	5
Missing Values (NaN) in Tables and Calculations	6
Nonlinear Curve Fitting: Fit Plot	
Specifying Custom Fit Equation	. 15
Using Spline for Baseline Subtraction	. 16
Guessing Peaks	
Predefined Fit Curves Equations	. 19
Export Curves as Table	
Setting Column Formula	
Integration	
Differentiation	
Fast Fourier Transform (FFT)	
Calculating Integrals and Statistics on Intervals using Fit Plot	
Axes Style Editing	
Adding and Arranging Curves on Figure Axes	
Adding and Arranging Axes Boxes on a Figure	
Using Figure Templates	
Drawing on Figures and Fit Plots, Image Zoom and Objects Selection	
Scale Scrolling for Data Navigation	
Reading Plot Data, Measuring Distances, Curves Selection	
Shifting Curves on Figure and Creating 2D Waterfall	
Colours and Opacity Adjustment	
Creating Transparent Figures and Fit Plots	
Using of Dimensions Toolbar	
Inserting Special Symbols and Greek Letters	
Advanced Typography Features	
Point, pt (unit of measure)	
Image Export	
Preview Image	
Copying Images to Clipboard	
MagicPlot Calculator	
Keyboard Shortcuts	. 56

MagicPlot User Guide

Compiled from online help on <date> © MagicPlot.com

System Requirements and First Launch

MagicPlot is a cross-platform application based on WJava technology. Java Runtime is included in the MagicPlot distributive for Windows and Mac OS X.

Running MagicPlot on Linux/Unix

You need Java Runtime Environment (JRE) of version 11 or later to run MagicPlot 3.0. You can install Java using the package manager or get a free compiled copy here: https://adoptopenjdk.net/.

Run MagicPlot using command: path-to-jre/bin/java -XX:MaxRAMPercentage=75 -jar MagicPlot.jar.

Here -XX:MaxRAMPercentage=75 means maximum heap memory usage 75% of free memory.

First Launch

- MagicPlot does not need any installation procedure.
- Place MagicPlot executable folder to the directory you prefer.
- MagicPlot preferences and registration data are stored in your operating system profile and are individual for each account.

Opening Projects on Double Click

Windows

To make Windows open your MagicPlot project files (.mppz) in MagicPlot just open context menu of one project file in Explorer and select Open With → Choose Program item. In the opened window press Browse button and choose MagicPlotPro.exe or MagicPlotStudent.exe file. Select the Always use the selected program to open this kind of file checkbox and click OK.

Mac OS X

MagicPlot project files (.mppz) will be automatically associated with MagicPlot by your operating system.

Getting Started: Tables, Figures, Fit Plots and Undo

MagicPlot Projects contain Tables, Figures and Fit Plots. MagicPlot Project files have .mppz extension.

- Tables contain numeric or text data.
- Fit Plots are intended for non-linear curve fitting and subtracting baselines.
- Figures are intended to graphically represent multiple data.

Sallery for 3.0 manual - MagicPlot 3.0						
Project Edit View Table Proc	essing Tools Help					
	R 🖻 🖻 🐂 🦳 🔭 🐼					
Times New Roman 💌 14	▼ □ B I O U E Ξ Ξ					
🗁 Gallery for 3.0 manual	Results					
▼ 🗁 Jet Ⅲ Jet	I Jet					
I Results I Cross-section	A Cross-section					
 ✓ Jet ✓ Jet with interpolation 						
🔀 Waterfall						

Close Unused Internal Windows

Feel free to close currently unused interval windows with Tables, Figures and Fit Plots. The data will not be deleted, the window will be closed only. You can open the closed window by double clicking on component in Project tree.

Where to start?

In most cases you may start with importing table from text file by clicking Project \rightarrow Import Text Table menu item.

Creating Figures and Fit Plots

The easiest way to create Figure or Fit Plot is the following:

- Select two columns (x and y) in Table containing your data
- Select Create Figure or Create Fit Plot item in the Table context menu

I Result	s			_ ×
	AX	BY		^
1		0.0060		1
2	1	f(x) Set Column Formula	Ctrl-F2	
3	1	🔀 Create Figure	•	Line
4	1	Add to Selected Axes	•	••* Markers
5	1			*** Line & Markers
6		🛃 Create Fit Plot	►	
7	1	Cut	Ctrl-X	📕 Area
8	1	Сору	Ctrl-C	Vertical Bars
9	1	Paste	Ctrl-V	Color Man
10	1			Color Map
11		Clear Selected	Delete	
12	1	Set Column Type	•	
13	1	Insert	•	*
	4	Delete		
		Sort Table		

You may also use Create Figure or Create Fit Plot buttons in the toolbar.

Enter Expressions in any Numeric Field

MagicPlot can evaluate simple expressions entered in any numeric text field (brackets are supported, see Expression Syntax for details.) For example, you can enter 12/pi in circle width and height fields in Dimensions toolbar if you want its perimeter to be equal to 12 (remember that $p=\pi d$, where p is perimeter and d is diameter):

Figure 1		×
	Dimensions × X: 1 Y: 1	*
	Width: 12/pi Height: 3.8197 Units: cm	

Importing Table from Text File (ASCII)

Use Project \rightarrow Import Text Table menu item to import table(s) from text file(s), also referred to as ASCII file(s).

You may select multiple files in opened standard file dialog by holding Ctrl or Shift.

- If you open multiple files, you can select the file to preview in files drop-down list (in Text Input Preview frame)
- If you select incorrect file(s) by mistake, click on Open icon to open file dialog once again and select other file(s).
- You can set Create Figure or Create Fit Plot checkbox to create Figure of Fit Plot after importing:
 - If you select Figure, the created Figure will contain all imported data from all files
 - If you select Fit Plot, one Fit Plot will be created for each imported file
- You can enlarge a part of the preview plot by selecting an area by mouse (scale box zoom tool). Use context menu of the plot to change scale zoom to default.
- F5 key reloads the text file or reloads the data from clipboard.

📕 Import	t Text Table(s)				×	
Text Input Preview (first 256 lines, → = tab)				File Format		
Results.txt 🔹 🚬			-	Encoding: <system default=""></system>	•	
1	X→Y			Read all lines Auto detect	-	
2	1.9999999999999	99996→-0.086908	313552	Exclude header lines: 3	ŧ	
3	1.917999999999	99997→0.0659427	762132			
4		99994→0.4188217		Get column names from line: 1	Ŧ	
5		99996→0.6961593		Separate names by: Delimiter Column wide 	dth	
6		99997→0.8799459		Column delimiter or reg. expr.: Auto detect	-	
7		99994→1.1055753			T	
8		99996→1.3644997		Decimal separator: Auto detect (. or ,)	-	
9		99997→1.3762263		In Project		
10 11	1.262→1.63892	99999→1.4863369		Create: Figure V Fit Plot(s) Line	•	
11	1.262→1.63692	91444641930	•	X: AX Y: BY Y Err: <none></none>	•	
Preview (y	ou can rename colum	B Y		E I I I I I I I I I I I I I I I I I I I		
1	2	-0.0869		1.5		
2	1.918	0.0659				
3	1.836	0.4188				
4	1.754	0.6962				
5	1.672	0.8799				
6	1.59	1.1056		0.5		
7	1.508	1.3645				
8	1.426	1.3762				
9	1.344	1.4863		0		
10	1.262	1.6389		-2 0 2	_	
11	1.18	1.4699	-	4	Ŧ	
Columns: 2	2; rows: 50	I		Import Cancel	1	

Command Line Arguments and 'Silent' Import

MagicPlot opens files which come as the command line arguments on launch. MagicPlot Project files (.mppz) are detected as projects, the all other files are treated as the text files and the Import dialog is opened. The text files will be imported in the current opened project.

The -silent key in command line forces MagicPlot to import text files without opening import dialog. The previously used import setting are used in such case. If Fit Plot or Figure creation was selected in Import dialog last time, the new plots will be created.

Example for Windows OS: MagicPlotPro.exe mydata.txt -silent

Please make sure that your firewall software does not block MagicPlot loopback (127.0.0.1) request.

Table Editing

In MagicPlot Tables are used to store numeric or text data depending on column type (numeric/text).

Data Types

MagicPlot supports these data types in Tables:

Format	Description
Numeric	64-bit double precision floating-point numbers (WIEEE 754)
Text	Unicode string with unlimited length

- Data type is set for entire columns. One column may not contain data with different types.
- Empty cells are equivalent to Not-a-Number values.
- Values from text columns are treated as empty cells if used as numbers.

Changing Column Type

Use Set Column Type menu in column context menu to change column type (numeric/text).

Columns Numbers

Columns are enumerated starting with 1. The first 26 columns are additionally denoted with Latin letters: A, B, C, ... Y, Z, 27, 28, 29, You can use either numbers or letters, addressing cells and columns in formulas.

Renaming Columns

Double click on column header to rename table column. You can also use Rename Column context menu item or press F4.

Moving (Reordering) Columns

Hold Alt key (Option on Mac, Meta/Win on Unix-like) and drag column header to rearrange table columns. If Alt key is not pressed, mouse dragging on header will select the columns.

Editing Table

You can edit table cell by double clicking on it. You can enter either a number or an expression using Expression Syntax.

Fit Column Widths

To fit the width of one column, double click on right separator line in table header. To fit several columns widths, select multiple columns and double click on one of column separators in table header.

See Also

- Setting Column Formula
- Expression Syntax
- Table Sorting
- Missing Values (NaN) in Tables and Calculations

Missing Values (NaN) in Tables and Calculations

In computing, NaN, which stands for Not a Number, is a value or symbol that is usually produced as a result of an operation on invalid input operands. For example, most floating-point units are unable to explicitly calculate the square root of negative numbers, and will instead indicate that the operation was invalid and return a NaN result.

An invalid operation is not the same as an arithmetic overflow (which returns a positive or negative infinity). Arithmetic operations involving NaN always produce NaN, allowing the value to propagate through a calculation so that errors can be detected at the end without extensive testing during intermediate stages. A NaN does not compare equal to any number or NaN.

How does a NaN appear?

There are three kinds of operations which return NaN:

- 1. Operations with a NaN as at least one operand, e.g. 1+NaN
- 2. Indeterminate forms
 - \circ Divisions 0/0, ∞/∞ , $\infty/-\infty$, $-\infty/\infty$, $-\infty/-\infty$
 - \circ Multiplications 0^{*}∞, 0^{*}(-∞)
 - ∘ Power 1[^]∞
 - $\,\circ\,$ Additions $\infty+$ ($-\infty)$, $\,$ ($-\infty)+\infty$ and equivalent subtractions.
- 3. Real operations with complex results
 - $\circ\,$ Square root of a negative number
 - Logarithm of a negative number
 - \circ Tangent of an odd multiple of 90 degrees (or $\pi/2$ radians)
 - \circ Inverse sine or cosine of a number which is less than -1 or greater than +1.

Examples

Expression	Result
0^0	1
0/0	NaN
sqrt(-1)	NaN
1/0	Infinity
-1/0	-Infinity

NaN in MagicPlot Tables

In MagicPlot NaN is also used to represent empty cells in Tables.

Statistical functions ignore NaN values in Tables.

NaN in Expressions

You can use predefined constants NaN, nan or NAN in expressions to specify NaN value.

The isNaN(x) function checks if the argument is NaN.

Example

If you set a Column Formula if (col(B) >= 0, col(B), NaN), it will return only positive values from column B. Negative values are replaced with NaN value. You can use this expression to filter negative values if you do not want to use them in future calculations. Note that "Not-a-Number returned at row #" warning can be shown for such expressions.

Nonlinear Curve Fitting: Fit Plot

Creating a Fit Plot

Nonlinear least squares data fitting (nonlinear regression) can be performed using Fit Plot. To create a Fit Plot, select your X and Y columns in Table, then select Table \rightarrow Create Fit Plot in the main menu, or use the same item in the Table context menu, or use Create Fit Plot button in the toolbar.

7/58

Result	s	_ ×		
	AX	В Ү 🔶		
1	2	0.0050		1
2	1.918	f (x) Set Column Formula	Ctrl-F2	
3	1.836	🔀 Create Figure	•	
4	1.754	Add to Selected Axes	•	
5	1.672	Add to beletted Ates		
6	1.59	😫 Create Fit Plot	•	/ Line
7	1.508	Cut	Ctrl-X	••* Markers
8	1.426			🖋 Line & Markers
9	1.344	Сору	Ctrl-C	
10	1.262	Paste	Ctrl-V	📕 Area
11	1.18	Clear Selected	Delete	Vertical Bars
17	1 098	Set Column Type	•	
	1	Insert	•	
		Delete	· ·	
		Delete		
		Sort Table		

MagicPlot has been verified with NIST Datasets

National Institute of Standards and Technology (NIST) has created the Statistical Reference Datasets Project which includes 26 datasets for testing the nonlinear fit algorithms. MagicPlot has been successfully tested on these datasets. Our report on MagicPlot testing with NIST datasets is available here: Report.

Fitting Methodology

'Nonlinear' means here that analytical fitting function depends nonlinearly on varying parameters (fit parameters). Fit procedure iteratively varies the parameters of the fit function to minimize the residual sum of squares. The nonlinear fitting algorithm needs the user to set the initial values of fit parameters.

To fit the data, implement these steps:


- 1. Create a Fit Plot, specify Y errors in Data tab of Curve Properties dialog for the data curve, if any
- 2. Specify fit function by adding Fit Curves
- 3. Specify initial values of fit parameters (drag curves or enter accurate values)
- 4. Specify used X data interval
- 5. Run fitting

You can undo fit and also undo changing initial parameters as any other action using Undo function. It is a handy feature when experimenting with different models and initial parameters.

Further reading

This manual does not completely cover the complex nonlinear fitting methodology. We recommend you to take a look at this book:

• H. Motulsky and A. Christopoulos, *Fitting Models to Biological Data Using Linear and Nonlinear Regression: A Practical Guide to Curve Fitting, 2004.*



Fit Function is a Sum of Fit Curves

MagicPlot considers fit function as a **sum** of Fit Curves. Ordinarily in peaks fitting each Fit Curve corresponds to one peak in experimental data. Click the Add button to add new Fit Curve to the list. There is a number of predefined Fit Curves types (Line, Parabola, Gauss, Lorentz, etc.) You can also create a Custom Equation Fit Curve and manually enter the formula. Baseline fitting components may be added to the fitting sum, too.

Fit Plot window contains the list of Fit Curves. Each Fit Curve in the list has three checkboxes:

Fit Curves Fit Intervals Report							
Туре	Legend	Show	Bas	Sum			
—Line	Curve 1		V				
	Curve 2	V		V			
Lorentzian-A	Curve 3	1		V			
Lorentzian-A	Curve 4	V		V			

- Show: Specifies whether to show this Fit Curve on the plot. Active only if Baseline checkbox is not set
- Baseline: Toggles the subtracting of this Fit Curve from experimental data. You also can use

- Residual button to subtract all Fit Sum from data
- Sum: Specifies whether to use this Fit Curve in sum fit function

Below the Fit Curves list, is a parameters table which shows names, values, and descriptions of parameters relating to the selected Fit Curve.

Fitting by Sum and Fitting One Curve

MagicPlot allows two alternatives buttons to run the fit:

- Fit by Sum button will fit the data with the sum of Fit Curves for which the Sum checkbox is set. Data interval from Fit Interval tab will be used. This button must be used for example to fit the spectrum with the sum of peaks.
- Fit One Curve button will fit the data with the one currently selected Fit Curve. The individual interval for each Fit Curve will be used. Set Edit Interval checkbox to edit individual interval for each Fit Curve.

Copying and Pasting Fit Curves

You can copy and paste Fit Curves from one Fit Plot to another Fit Plot or Figure. You can also paste the copied Fit Curves to the same Fit Plot to create a copy.


- The copy of Fit Curves with the same parameters and styles will be created if you paste Fit Curves to a Fit Plot.
- A link to the source Fit Curves will be inserted if you paste Fit Curves in a Figure.

Fit Curves Reordering

You can reorder Fit Curves by dragging them in the table. The data curve is always drawn the first and fit sum is drawn the last.

Setting Initial Values of Parameters

Nonlinear fitting assumes that certain initial values of parameters are set before fitting. This procedure is very easy if you use Fit Curves of predefined types (not custom equation): you can drag curves on the plot. Initial parameters values for each Fit Curve can also be set in the parameter table.



Adjusting Parameters with Mouse Wheel

You can adjust Parameters in the table using mouse wheel scrolling when the mouse cursor is on the desired parameter: Hold Ctrl key (Cmd key on Mac) and scroll. If the Shift key is also pressed the parameter step for one wheel 'click' will be increased.

Guessing Peaks

If you are fitting a spectrum with multiple peaks, MagicPlot may automatically add and approximately locate peaks before fitting. See <u>Guessing Peaks</u> for details. Guessed peaks should be used only as of the initial estimate for fitting: don't forget to click the Fit button after peaks are added.

Parameter Locking

You can lock (fix) parameter(s) to prevent varying this parameter(s) during the fit and to prevent its changing due to set initial values by mouse dragging (for built-in functions). Set the checkbox in Lock column in the parameter list to lock parameter.

Param	Description	Value	Lock	StdDev
a	Area	12.58158		0.71975
x0	X Position	2994.922		0.28816
dx	HWHM	11.86179		d 0.35653

Parameters Joining

MagicPlot allows joining (sometimes referred to as coupling, binding, linking) of fit parameters of different Fit Curves. See Joining the Parameters of Fit Curves for details.

Weighting of Data Points Using Y Errors

MagicPlot allows the weighting of data points with Y error data. You can specify Y error data in Fit Plot properties dialog. If no Y error data are specified weighting is not used.

Weights are calculated as 1 / Y_{error}^2 for every point. See Fitting Algorithm and Computational Formulas for details.

Weights must be positive and finite for all points so the Y error values must be positive and non-zero (to prevent infinite weights). MagicPlot checks this condition before fitting and shows an error message if Y errors cannot be used to compute weights.


Specifying Fit Intervals

You can set the X intervals of the data which will be used for fitting. Data points outside these intervals are not used to compute the minimizing residual sum of squares. You can use this feature if some data points (especially in the beginning or the end) are inaccurate, e.g. noisy.

Select Fit Interval tab to set intervals visually or edit accurate borders values in the table.

- Double click on the interval to split it
- Drag the interval border to move it. If intervals intersect, they will be merged
- Use context menu on the plot to create, delete and split intervals

Note: Data intervals from the Fit Interval tab are used for fitting Sum only. To set individual data intervals for the one Curve fitting use Edit Interval checkbox.



Baseline Fitting and Extraction

Fit Interval is also usable when baseline fitting. Before baseline fitting, you can specify the interval which does not contain any signal points and contains baseline only. Set Baseline checkboxes at baseline Fit Curves after baseline fitting to subtract baseline from data. Then specify the whole interval and fit the data.

Note that if you use data processing (integration, FFT, etc.) on Fit Plot, then the difference between

the data and baseline curves (which you do see on the plot) will be processed. You can use this behavior to exclude baseline from data before integrating, see Integration for more information.

'Data-Baseline' Table Column

The 'Data-Baseline' column is appended to the Table with initial (X and Y) data when you create a Fit Plot. The 'Data-Baseline' column contains the difference between initial Y data and baseline approximation (the sum of Fit Curves for which Baseline checkbox is set). It is 'Data-Baseline' column that is actually plotted on Fit Plot as data.

Use 'Data-Baseline' column in Table if you want to process the data without baseline. This column is also used as initial data if you use Processing menu when Fit Plot is active.

Viewing the Residual Plot


Residual means here the difference between initial data, baseline function and Fit Sum function. MagicPlot offers two different ways to view the residual:

- Press and hold the Residual button. The residual will be shown while the button is pressed. You can use either mouse or space key (if the button is selected) to hold Residual button.
- You can either set Baseline checkboxes for all summed Fit Curves to subtract them from data and explore the residual plot

Fitting

To execute the fit click the Fit by Sum button of Fit One Curve button (see below).

MagicPlot indicates the fit process with a special window. Fitting curves are periodically updated on the plot while fitting so you can see how fit converges.



MagicPlot shows the current iteration number and deviation decrement with two progress bars while the fit is performed. The fit process stops when one of these progress bars reaches the end.

You can see two buttons on fit progress window:

- Break Iterations: Breaks iterations after current iteration. Use this button if you suspect that further iterations will not change the result.
- Undo Fit: Breaks iterations and reverts fit parameters to their initial (before fit) values. Use this button if you see that fit process converges to wrong result; change initial values of

parameters and run fit again.

Fitting One Curve

You can use MagicPlot to fit the data with single selected Fit Curve by pressing Fit One Curve button. In this case, a specific data interval for each Fit Curve is used and the main fitting data interval (from Fit Interval tab) is ignored. Select Edit Interval checkbox in the bottom of the Fit Plot panel to set specific fit intervals for each Fit Curve.

Because of using individual data interval this method is useful for baseline fitting. In order to fit baseline specify the intervals which do not contain signal (peaks) and contain only noise.

у (x) =
a / (dx*pi*(1 + (x-x0)^2 /
dx^2))
Amplitude = 0.33763
Join V Edit Interval Fit One Curve

Why My Fit is Not Converged?

In some cases, the fit procedure may fail to find the optimal parameters values. The actual mathematical reason for this error is the impossibility to invert the matrix α calculated from partial derivatives of the fit function with respect to fit parameters. This inverted matrix is used to compute the new values of parameters for the next step of fit (like gradient descent). In most cases, this error occurs when the matrix α is ill-conditioned or nearly singular and the inverse cannot be calculated accurately enough with used floating-point arithmetic.

The origin of this error may be:

- Fit is not converged through one or more parameters: some parameters were taking unrealistically great values during iterations. There is no local minimum of residual sum of squares near the initial values of these parameters. MagicPlot highlights the suspicious Fit Curve in this case.
- Mutual dependency exists between some parameters. The algorithm cannot resolve which parameter to vary.
- Fit function is ill-conditioned: the minimized residual sum of squares depends on some parameters much more than on other ones.
- Numeric overflow (or underflow) when calculating fit function with initial parameter values or on the next steps.

Try one of the following:

- Specify more accurate initial values of parameters.
- Simplify the fit function (e.g. remove some peaks).

• Lock some parameters.

See Also

- Fitting Algorithm and Computational Formulas
- Specifying Custom Fit Equation
- Using Spline for Baseline Subtraction
- Joining the Parameters of Fit Curves
- Guessing Peaks
- Predefined Fit Curves Equations
- Calculating Integrals and Statistics on Intervals using Fit Plot
- Export Curves as Table

Specifying Custom Fit Equation

To specify custom fit function formula, press Add button and select Custom Equation in popup menu.

- Enter your formula in y (x) = text field below. Use x as fit function argument. See Expression Syntax for details.
- You may recall last entered custom fit functions using Recently Used Custom item in Add popup menu.

						□×
		Fit Curves	Fit Inte	rvals Re	port	
B-Baseline Curve 4		Туре	e Leger	d Show	Baseli	. Sum
Fit Sum		- Custon	n Curve 4			 Image: A start of the start of
		• •	Data 📒	• 🗸 Sum	Re	sidual
	0 0 0	Add 🔻	Guess		Fit b	y Sum
		Parameter	Descripti	Value	Lock S	Std. Dev.
		Α		0.67		
		omega		0.5993		
	÷	phi		0.4021		
	-	y (x) =		000		√
3 4		A*sin(o	mega* <mark>x</mark> +	phi) /	x	
		Join	Edi	t Interval	Fit One	Curve

Fit Parameters

You can introduce Fit Curve parameters with any names except argument x, and constants like e, pi (see predefined constants for details):

- Parameters names are case-sensitive (a and A are different parameters).
- Parameters names lengths are not limited.
- Begin names with letter or _ sign. You can use numbers in the middle or in the end of the name: a1, a_1, A1, a1t, but the names like 1a are not allowed.

The parameters you introduce in formula will automatically and immediately occur in parameters list, you do not need to enter parameters names in the list manually. Random values are used as the initial values of parameters. Do not forget to set more relevant initial values, otherwise fit algorithm may fail.

Adjusting Parameters with Mouse Wheel

You can adjust Parameters in table using mouse wheel scrolling when mouse cursor is on the desired parameter: Hold Ctrl key (Cmd key on Mac) and scroll. If Shift key is also pressed the parameter step for one wheel 'click' will be increased.

See Also

- Nonlinear Curve Fitting: Fit Plot
- Using Spline for Baseline Subtraction
- Predefined Fit Curves Equations

Using Spline for Baseline Subtraction

You can use cubic spline to subtract baseline on Fit Plot. To create spline curve click on Add button in Fit Curves tab of Fit Plot and select Spline menu item.


Do not use splines to subtract baselines which can be fit well enough with Line curve (line or constant baseline). You may mistakenly subtract wide peaks using spline. In some cases Parabola curve may be more suitable.

Editing Spline

Created spline has three anchor points by default. You can move, add and remove anchor points:

- Move anchor point with mouse
- Double click on spline curve to add new anchor point
- Double click on anchor point to remove it


Set Baseline checkbox in spline row in fit curves table to subtract spline from data.




Fitting with Spline

Spline anchor point (x, y) coordinates are treated as fit parameters so you can perform fitting with spline although we don't recommend this technique. Fitting the baseline with some adequate model function is preferred.

It is recommended to set appropriate fit intervals which contain only baseline without peaks. In such case Fit One Curve button is more acceptable than Fit by Sum button, because the individual interval for current curve will be used and the interval from Fit Interval tab (which is used to fit by sum of curves) is ignored. Select spline curve and set Edit Interval checkbox in the bottom of the panel to edit spline interval, then click on Fit One Curve button. The anchor point coordinates will be varied but the number of points will remain. You also can lock some parameters (usually *x* coordinates) by setting Lock checkboxes in parameters table.






- Nonlinear Curve Fitting: Fit Plot
- Specifying Custom Fit Equation
- Guessing Peaks
- Predefined Fit Curves Equations

Guessing Peaks

MagicPlot can approximately locate peaks in spectrum. To locate peaks click on Guess button in Fit Curves tab of Fit Plot. Peaks are added at position of global extremum of data-baseline with previous peaks subtracted.

When Guess Peaks window is open you can see the preview of guessed peaks on Fit Plot. This preview is updated every time you change the parameters in the window.



- Nonlinear Curve Fitting: Fit Plot
- Specifying Custom Fit Equation
- Using Spline for Baseline Subtraction
- Predefined Fit Curves Equations

Predefined Fit Curves Equations

All predefined Fit Curves are listed in this table. You also can specify custom fit equation. Unlike custom fit equations these curves can be adjusted with mouse on Fit Plot.

Name	Formula	Parameters Additional Meaning Properties
Line	y = ax + b	a — linear b — constant
Parabola	$y = a_x^2 + b_x + c$	$\begin{array}{c} a - \\ quadratic \\ b - linear \\ c - constant \end{array} \begin{array}{c} Vertex: \\ v_0 \equiv c - \frac{b_b^2}{2\pi} \end{array}$

Name	Formula	Parameters Meaning	Additional Properties
Spline	Natural cubic spline, on each <i>i</i> -th piece: $y_i = a_i + b_i x + c_i x^2 + d_i x^3$	xN — anchor point x- coordinates yN — anchor point y- coordinates	
Gaussian	$y = a \exp\left(-\ln\left(2\right) \left(\frac{x - x_0}{dx}\right)^2\right)$	a — amplitude dx — half width at half maximum (HWHM) x0 — maximum position	Area (integral): Standard deviation: $\$ \equiv \sqrt{\frac{4x}{2} \frac{\pi}{1 + 2^2}} a dx$
Gaussian-A (area-normalized)	$y = \sqrt{\frac{\ln 2}{\pi}} \frac{a}{dx} \exp\left(-\ln\left(2\right)\left(\frac{x-x_0}{dx}\right)^2\right)$	a — area (integral) dx — half width at half maximum (HWHM) x0 — maximum position	Amplitude: Standard deviation: $A = \sqrt{\frac{dx_{\ln 2}}{2 \ln 2}} \frac{a}{dx}$
Lorentzian	$y = a \frac{1}{1 + \left(\frac{x - x_0}{dx}\right)^2}$	a — amplitude dx — half width at half maximum (HWHM) x0 — maximum position	Area (integral): $S = \pi a dx$
Lorentzian-A (area-normalized)	$y = \frac{a}{\pi dx} \frac{1}{1 + \left(\frac{x - x_0}{dx}\right)^2}$	a — area (integral) dx — half width at half maximum (HWHM) x0 — maximum position	Amplitude: $A = \frac{a}{\pi dx}$
Gauss Derivative	$y = -2\ln\left(2\right) \frac{a\left(x-x_{0}\right)}{dx^{2}} \exp\left(-\ln\left(2\right)\left(\frac{x-x_{0}}{dx}\right)^{2}\right)$	Parameters are the same as for original Gaussian: <i>a</i> — amplitude <i>dx</i> — half width at half maximum (HWHM) <i>x0</i> — center position	Area of original Gaussian (second integral): Standard deviation: Peak-to-peak horizontat; adx Peak-to-peak vertical $p_x = \sqrt{\frac{2}{\ln 2}} \frac{dx}{dx}$ $p_y = 2 \sqrt{\frac{2\ln 2}{e}} \frac{a}{dx}$

Name	Formula	Parameters Meaning	Additional Properties
Lorentz Derivative	$y = -2a \frac{x - x_0}{dx^2} \left(1 + \left(\frac{x - x_0}{dx}\right)^2 \right)^{-2}$	Parameters are the same as for original Lorentzian: <i>a</i> — amplitude <i>dx</i> — half width at half maximum (HWHM) <i>x0</i> — center position	Area of original Lorentzian (second integral): Seak to peak horizontal: Peak to peak vertical: $p_{y} = \frac{3\sqrt{3}}{4} \frac{a}{dx}$

- Nonlinear Curve Fitting: Fit Plot
- Using Spline for Baseline Subtraction
- Guessing Peaks

Export Curves as Table

Fit Curves and Fit Sum are treated as function equations in MagicPlot Fit Plots. But in some cases (e. g. to export and plot fit data with other application) you may want to create (x, y) table with Fit Curves y-values. For this purpose use Tools \rightarrow Export Curves as Table menu item when Fit Plot is active. This dialog is also available for Figures.

You can either add new Table to a Folder in current Project or export table to a text file.

Fit Curves Export Data Export							
Export Shown Fit Curves Export Initial Data							
💿 Use Data X Column 👿 Export Data - Baseline							
Man	ual X: X from:	-651	04.1666499	to:	65102.17982859	V Export Resi	dual
	N Points:	1000		or ΔX :	130.3366831617	<u> </u>	
Created Ta	able Preview						
	A Data X		B Data Y		C Data Y-Baseline	D Residual	E Fit Curves X
1	-65104.	1666		0.0038	0.0038	0.0038	-65104 🔺
2	-65102.	1798		0.0038	0.0038	0.0038	-649
3	-65100	. 193		0.0038	0.0038	0.0038	-64843
4	-65098.	2062		0.0038	0.0038	0.0038	-64713
5	-65096.	2194		0.0038	0.0038	0.0038	-64582
6	-65094.	2325		0.0038	0.0038	0.0038	-64452
7	-65092.3	2457		0.0038	0.0038	0.0038	-64322
8	-65090.3	2589		0.0038	0.0038	0.0038	-64191
9	-65088.3	2721		0.0038	0.0038	0.0038	-64061
10	-65086.3	2853		0.0038	0.0038	0.0038	-63931
11	-65084.3	2984		0.0038	0.0038	0.0038	-63800
12	-65082.3	3116		0.0038	0.0038	0.0038	-63670
13	-65080.3	3248		0.0038	0.0038	0.0038	-63540
14	-65078	338		0.0038	0.0038	0.0038	-63400
	· [ŕ

Page moved to Expression Syntax.

Setting Column Formula

There are two ways to set formula for column evaluation:


1. Select column and write formula in formula string.

🔊 12-10-10 - MagicPlot Pro 2.3						
Project Edit View Table Proc	essing Tools H	Help				
Di 🗠 🖾 Di 🗘 🕅 🔛 🗠	💧 🕯 🔎	e h 🔍 🌒		⊠ 🖾 🖾 / т →		L
$\mathbf{I}_{\mathbf{k}} \mid \mathbf{f}(\mathbf{x}) \times \mathbf{t} \mid \mathbf{O} Col(D) = \mathbf{sq}$	rt <mark>(</mark> col(B)^2	+ col(C)^2 <mark>)</mark>				
Project						
12.10.10 12.10.10 12.10.10 FFT of 12.10.10						
FFT of 12.10.10 D A	A		В	C	D	
	1	3.1988e-4	-1.0601	-0.075	1.0628	
FFT of 12.10.10 H	2	3.2756e-4	-1.0552	-0.0971	1.0597	
I	2	2 250AA A	1 0527	0 1026	1 0500	

2. Use Table \rightarrow Set Column Formula menu item to open column formula dialog window. See Expression Syntax for details.

Thu Apr 25 10:01:29 2024

23/58



Row Index

Variable i contains the current row index. Rows are enumerated from 1.

Rows Evaluation Order

Rows are always evaluated one after another from the first to the last in the specified range. Accordingly the row number i is incremented after each step.

Example

• You can use this behavior to calculate Wfactorial: set 1 in the first row of column A and after that set formula cell(A, i-1) * i and rows interval from 2 to 100. Note that formula is to be set for rows beginning from the second, and not from the first. You will get the factorial of row number (i).

Using Table Data

There are two functions to obtain current table cell values in formula:

- col(A) returns the value of cell in column A in the current (i-th) row. Equivalent to cell(A, i).
- cell(A, 3) returns the value in column A and row 3.

You can use either upper-case letters (A...Z, e.g. col(B)) or numbers (1, 2, 3, ..., e.g. col(1)) in columns numeration in arguments of col and cell functions.

Example

• col(A) + 15 + cell(B, i+1)

Auto Recalculation on Data Change


MagicPlot can automatically recalculate formula when data in used columns are changed. Set Auto Recalculate checkbox to enable this feature.

Example

• Set formula col(A)*2 for column B and set Auto Recalculate checkbox. Column B will be recalculated if you change values in column A or column A is updated by other formula or processing algorithm (e.g. integral, derivative of other column).

Formula Menu in Column Context Menu

You can edit column formula and change auto recalculation mode from column context menu or menu Table. Select exactly one column and open context menu to view this menu items.



"Argument is out of range at row #" Warning

Some mathematical functions can be defined only on a certain interval. For example, square root (sqrt(x)) is not defined for negative numbers (all calculations in MagicPlot are made in real numbers, not complex). Hence if the argument of sqrt is negative, a Not-a-Number (NaN) is

The calculations are not terminated if NaN value occurs in some row(s).

In some cases you may want to check if a NaN values occurs in calculations. MagicPlot shows the warning "*Argument is out of range at row #*". This row number is the **first** row in which NaN value was returned. MagicPlot also highlights the function or operator which first produces NaN value.

See Also

• Expression Syntax

Integration

Open Table or Figure or Fit Plot with initial data and select Processing \rightarrow Integrate menu item.

f(x) Integral	1000					×
Preview				Input		
F F				X Data:	AX	•
15 -				Y Data:	CY	•
	- N			Parameters —		
10-			~	No parameters a	vailable.	
5 -						
	and the second s					
0						
-100000	-50000 0	50000 10	000(-			
•			•			
Plotting: 📝 Figure	Fit Plot(s)			📝 Auto Recalcula	ite OK	Cancel

Baseline Correction

If your initial data to be integrated contains a baseline (usually constant or linear), you may want to subtract it from data **before** integrating. (A constant baseline will result in linearly growing integral.)

In such case the algorithm may be the following:


- 1. Create Fit Plot with your initial table data
- 2. Add a Fit Curve which simulates the baseline. You may specify a custom equation
- 3. Specify Fit Interval so that it contains only noise points
- 4. Fit the data by clicking Fit Sum button
- 5. Subtract the baseline fitting curve from data by checking Baseline checkbox in curves list

6. Use menu Processing \rightarrow Integrate to integrate the plotted data without baseline.

Algorithm

To perform integration you should specify two columns: *x* and *y*. Missing values are ignored.


MagicPlot uses Wtrapezoidal rule to compute the integral:



Differentiation

Differentiation

Open Table or Figure or Plot with initial data and use Processing \rightarrow Differentiate menu item.



Algorithm

To perform differentiation you should specify two columns: x and y. Missing values are ignored.

MagicPlot uses W central difference formula to compute the derivative:

First and
$$x_{i+1}^{y_i \neq 1} = x_i^{y_i = y_i = 1} (x_{i+1}^{y_i = y_i = 1}, x_{i-1}^{y_i = y_i = 1})$$
, are computed as follows:

$$\sum_{y'_{1}}^{y} = \frac{y_{A}(y_{1})}{x_{2}^{-x_{1}}}, \quad y'_{N} = \frac{y_{N} - y_{N-1}}{x_{N}^{-x_{N-1}}}$$

- Data Processing and Auto Recalculation
- Integration

Fast Fourier Transform (FFT)

Open Table or Figure or Plot with initial data and use Processing \rightarrow Fast Fourier Transform menu item to perform **WFFT**.

Fast Fourier transform algorithm computes discrete Fourier transform exactly and is used to considerably speed up the calculations.

Note that FFT is not an approximate method of calculation.

х f(x) FFT Preview Input A Time Sampling: 0.03 ٠ • BRe Real: Ŧ C Im Imaginary: Ŧ 0.02 Parameters Sampling Interval: 5.12001310723355e-6 0.01 Direction: Forward Inverse 1/N in Forward Transform 0 Center Zero Frequency Factor in forward: () -1 (Default) +1 -0.01 -100000 -50000 0 50000 10000 -• ъ Plotting: 📝 Figure 📄 Fit Plot(s) Re, Im, Abs 👻 Auto Recalculate OK Cancel

Parameters

Sampling Interval	Sampling interval of original data Δt is used to compute the data in resulting sampling column. MagicPlot calculates sampling interval as a difference between second and first values in Sampling column. You can set sampling interval manually in Sampling Interval field. Note that using of discrete Fourier transform implies that the samples in your original data are equally spaced in time/frequency, i.e. the sampling interval is constant. If the sampling interval is varying or real and/or imaginary data contains empty cells in the middle, the result of discrete Fourier transform will be incorrect.
Real, Imaginary	Columns with real and imaginary components of data. If your data is purely real, select <none> imaginary item</none>
Forward / Inverse	Transform direction (here Inverse also equals to Backward)

1/N in forward transform	Divide forward transform result by number of points <i>N</i> (see formulas table). If your original data is real, you may want to additionally multiply the result by 2 to get the true amplitudes of real signal. Also referred as Normalize in some other applications.
Center zero frequency	If selected, after forward Fourier transform the two parts of spectrum will be rearranged so that the lower frequency components are in the center; the opposite rearrangement of spectrum will be done before inverse transform if any. Also referred as Shift FFT in some other applications.

Algorithm

MagicPlot uses the algorithm of FFT that does not necessarily require the number of points *N* to be an integer power of 2, though in such a case evaluation is faster. MagicPlot uses jfftpack library (a Java version of fftpack).

Discrete Fourier Transform Formulas

By default MagicPlot uses 'electrical engineering' convention to set the sign of the exponential phase factor of FFT: forward transform is computed using factor -1. Most scientific applications use factor -1 in forward transform as MagicPlot does by default. But note that the sign of exponential phase factor in Numerical Receipts in C, 2nd edition, p. 503 and in MATLAB package in forward transform is +1.

Factor -1 (Default)							
1/N in forward transform	Forward Transform (Signal→Spectrum)	Inverse Transform (Spectrum→Signal)					
Checked (Default)	1 N	N					
Unchecked	$C_{\mu} = \frac{1}{N} N c_{\mu} e^{-2\pi i k n / N}$	$c_{n} = \sum_{N} C_{k} e^{2\pi i k n N}$					
$C_n = \sum_{k=0}^{n-1} c_k e^{-2\pi i kn/N} c_n = \frac{1}{N} \sum_{k=1}^{n-1} C_k e^{2\pi i kn/N}$ Factor +1 (Scientific)							
1/N in forward transform	Forward Transform (Signal→Spectrum)	Inverse Transform (Spectrum→Signal)					
Checked (Default)	1 N	<u>N</u>					
Unchecked	$C_{\mu} = \frac{1}{N} N c_{\mu} e^{2\pi i k n / N}$	$c_{n} = \sum_{N} C_{k} e^{-2\pi i k n / N}$					
	$n N \sum_{k=1}^{n} 2\pi i kn/N$	1_{k} $-2\pi i kn/N$					

Here c_n are complex signal components and C_n are complex spectrum components, n = 1...N. The only difference is in the sign of exponential phase factor and 1/N multiplier.

Note: if you expect to get the original data when doing an inverse FFT of forward FFT, set the 1/N in Forward Transform, Center Zero Frequency and Factor options the same for forward and inverse transforms.

Amplitude and Phase Columns Formulas

Because of using watan2 function the phase is unwrapped and is in range $(-\pi, \pi]$. The result of atan2 (y, x) is similar to calculating the arc tangent of y/x, except that the signs of both arguments are used to determine the quadrant of the result.

Sampling Column Formulas

Sampling column contains frequency samples if forward transform is performed and time samples in case of inverse transform.

Center zero frequency	Formula	Sampling Column Values
Unchecked	n-1	1 2 N-1
Checked	$f = \frac{1}{m - M - M t/2}$	$0, \frac{1}{NV/2t}, \frac{1}{N\Lambda t}, \frac{1}{N/2}$
	f =	- <u> </u>

Here Δt is given sampling interval of initial data (time for FFT and frequency for IFFT), n = 1...N.

Missing Values in the Original Data

Fourier transform implies that the original samples are uniformly distributed in time (for forward transform) or frequency (for inverse transform).

- Missing values in the middle or in beginning of original data columns are treated as zeros, the result of Fourier transform may be incorrect.
- Missing values in the end of the column are ignored.

See Also

• Data Processing and Auto Recalculation

Calculating Integrals and Statistics on Intervals using Fit Plot


Setting of intervals in Fit interval tab of Fit Plot was initially intended for specifying the range of data which are used for fitting by sum of fit curves. However, this tab can also be used to calculate integrals and statistics on these intervals. Data-Baseline is used to calculate the results.

Peak Moments

MagicPlot can integrate data on selected intervals and calculate peak moments (x mean, variance, skewness, kurtosis). Spectrum line is treated as probability distribution curve: x values are treated as 'independent variable' and y values are treated as 'probability'. Standard statistical formulas are used to calculate moments (see below).

Statistical data and integrals are automatically updated if x or y data are changed or intervals are

changed.



All statistical data are summarized in the intervals table:

From	То	First Row	Last Row	Integral	X Mean	Variance	Std.dev.	Skewness	Kurtosis	Y Sum	Points
298.6059	380.1047	16461	16480	6.3699	341.6323	128.0854	11.3175	8.7703e-4	0.6547	0.1588	20
386.1791	438.3181	16483	16495	3.0123	414.6365	68.0536	8.2495	-0.3499	0.0449	0.0752	13
453.5042	487.4198	16500	16507	1	469.668	35.0647	5.9215	0.1509	-0.2173	0.0255	8

Managing Intervals

Move interval borders with mouse. Double click on interval to split it at desired position. Right click opens context menu from which new intervals can be created on free space and existing intervals can be deleted or split.

Relative Integrals Calculation

MagicPlot can calculate relative integrals to compare the relative intensity of spectrum lines. To compute relative integrals set Relative integrals checkbox. MagicPlot designate the smallest integral as 1, but you can enter a custom value. If you want to set not the smallest integral as a reference point, enter 1 first and then enter the value of desired integral relative to 1 into this field, so that other integrals will be calculated relative to this new value.

Computational Formulas

Central moments are calculated as follows (see table). All sums are calculated using W compensated summation. Central moments are calculated on second pass after Mean calculation.

Property	Formula
n	The number of non-NaN (x,y) points
Y Sum (normalization)	s= F n
X Mean (first moment)	$\sum_{i=1}^{n-L_{y}} i$
2, 3, 4 th WCentral momen	ts $\nu_1 \doteq \sum_{x, y, x}$
MagicPlot uses the followin	ng formulas calculate intervals statistics: 4
Property	<u> </u>
Intodral	Calculated using Trapezoidal rule
X Mean (expected value)	<i>u=v</i>
Variance	$\frac{1}{2}$ n
Standard deviation	$\sigma = \frac{1}{n-1} \mu_2$
Skewness	$\sigma = \sqrt{\sigma_1^2}$
Kurtosis	
See Also	$\gamma_{1} = \frac{\sqrt{n!(\bar{n} \perp_{1})}}{\sqrt{n}} \frac{\mu_{1}}{(n-1)} \frac{\mu_{2}}{(n-1)} \frac{\mu_{3}}{(n-1)} \frac{\mu_{4}}{\sigma^{4}} - 3(n-1)}{\sigma^{4}}$

- Nonlinear Curve Fitting: Fit Plot
- Using Spline for Baseline Subtraction
- Descriptive Statistics

Axes Style Editing

Axes style can be set in Figure Properties window (or Fit Plot Properties for Fit Plot). This window contains multiple tabs with axes drawing settings.

K Figure Properties: Figure 1								
Canvas Axes Properties Templates								
Axes	Components Axes General Ticks & Grid Axis Style							
Axes 1	X Axis	Ticks Positions				Grid		
Axes 2	Y Axis	Major Ticks				Major Grid		
	⊙ Desired Number 7					Style -		
		 Exact Increment Manual First Tick 				Width, pt 0.5 👻		
						Minor Grid		
		Minor Ticks				Style		
		Number of Ticks				Width, pt 0.1 👻		
	Custom Grid Lines							
		X Position	Bottom L	Top Label	Line	Color	Style	Width
		3015	х		V		<u> </u>	- 1.0
Add 🔻								
Delete								
·								Close

Adding and Arranging Curves on Figure Axes

The best way to create a Figure with desired data is to select x and y data columns in Table and use Create Figure in Table context menu.


There are different ways to add data to existing Figure:

- Select x and y columns in table with data, open table context menu (right click) and select Add to Selected Axes sub-menu. All currently opened Figures are listed in this sub-menu.
- Open Figure Properties window and go to Axes Properties → Components tab. Here you can select the Table in the project tree and press Add to Axes button.
- Copy and paste Curve from Fit Plot or another Figure to your Figure.

You also can add Fit Curves or Fit Sum from Fit Plot to Figure.

Changing Curves Drawing Order

To change Curves drawing order and legend entries order open Figure Properties dialog and go to Axes Properties \rightarrow Components tab. Drag rows in table to reorder. You can also use Up and Down buttons or press Alt + up/down keys (Option + up/down keys on Mac) to move selected row in table up or down.





- Creating a Figure
- Adding and Arranging Axes Boxes on a Figure
- Specifying Axis Multiplier, Prefix and Suffix
- Shifting Curves on Figure and Creating 2D Waterfall
- Using Figure Templates

Adding and Arranging Axes Boxes on a Figure

You can add a new Axes box to a Figure using the Add menu either in the Figure window or in the Figure properties dialog.

The Add & Arrange Axes as Table menu item can also be used for arranging of the existing Axes boxes as a table.





'Add and Arrange Axes as Table' Dialog

This dialog opens by selecting Add & Arrange Axes as Table menu item. It may be used for adding new Axes boxes and for arranging the existing Axes boxes without adding a new one.

Thu Apr 25 10:01:29 2024


35/58

Add and Arrange Axes as Table					
Arrangement		Margins			
Columns	Þ ≑	Тор	10		
Rows	2	Bottom	10		
-Axes Spacing -					
Horizontal	7	Left	10		
Vertical	0	Right	10		
2 new axes will be added Units % of Canvas OK Apply Cancel					

Moving and Resizing of an Axes Box

Axes box can be moved and resized as any other drawn object on the Figure canvas

- 1. Click on the Axes box border to select it. The green markers identifying your selection appear.
- 2. Drag Axes box border to move the Axes box on Canvas.
- 3. Draw border marker to resize Axes Box.



The Using of Dimensions Toolbar toolbar can also be used to set exact Axes box size and position. Open the Dimensions toolbar and select an Axes box to edit the values.


上 Dime	ensions	x
X:	20.0272	
Y:	0.5621]
Width:	3.0507	ത
Height:	3.2424	
Units:	cm	

- Creating a Figure
- Adding and Arranging Curves on Figure Axes
- Specifying Axis Multiplier, Prefix and Suffix
- Shifting Curves on Figure and Creating 2D Waterfall
- Using Figure Templates
- Drawing on Figures and Fit Plots, Image Zoom and Objects Selection

Using Figure Templates

Figure Templates is a powerful tool for reusing axes layout of previously created Figures. To use Figure Templates, open Figure Properties window and select Templates tab.

Templates are stored in a special folder in your operating system account profile. Project files do not contain templates; changes in Projects do not affect Templates.



Saving Template from Figure

To create a template from Figure open the Figure Properties window, select Templates tab and press 'Save Template' button. Then enter the new template name in opened dialog window.

MagicPlot always saves all available information in the template (not regarding on checkboxes state).

Applying Template to a Figure

To apply template to figure open the Figure Properties window and select Templates tab. Select desired template in the saved templates list. Then check or uncheck boxes with features to apply and click on 'Apply Template' button.

When you apply a template to Figure, the properties are copied from template to Figure. Note that the Figure style will not be changed if you change the template *after* you have applied it to Figure. The project file is standalone and you do not need the template to open project.

You can undo applying template in a standard manner (no need to close the Figure Properties window).

See Also

- Creating a Figure
- Adding and Arranging Axes Boxes on a Figure

- Adding and Arranging Curves on Figure Axes
- Specifying Axis Multiplier, Prefix and Suffix
- Shifting Curves on Figure and Creating 2D Waterfall

Drawing on Figures and Fit Plots, Image Zoom and Objects Selection

You can draw the following kinds of objects on Figures and Fit Plots:

- Text labels with formatting support
- Lines
- Arrows
- Rectangles
- Ellipses
- Inserting images



Select an appropriate instrument in the toolbar to draw an object.


The properties of selected objects can be changed in the inspector toolbar (the second row of toolbar).

Image Zooming

If you need to precisely draw some small objects you can zoom in the image using slider in right bottom (Pro only).

There are several alternative ways to change the image zoom:

- Scroll the mouse wheel at the image zoom slider
- Ctrl+scroll (Cmd+scroll on Mac) mouse wheel at blank part of plot (outside all axes boxes)
- The button 1x and Alt+click (Option+click on Mac) on plot fits the image to the window.



Do not Confuse Scale Scrolling and Image Zoom


- Scale scrolling affects the x/y scale minimum and maximum values. Use scale scrolling for data navigation
- Image zoom enlarges the entire image. Use image zoom for accurate drawing of small objects.

Objects selection

Every object can be selected by clicking on its border or inside it. Hold Ctrl key (Windows, Linux) or Shift key (Mac OS) and click another object to add it to current selection.

Moving an Object Forward or Backward

When objects overlap, you can change the order of objects drawing. Use Bring to Front and Send to Back items in object context menu (right click on object to open menu).




Changing Curves Order on Figure

You can change the order of drawing the curves on Figure. The curves order can be set in Figure Properties window, Axes Properties tab \rightarrow Components tab. Select desired curves in list, then

hold Alt and press up/down arrow keys. You may also use Move Up and Move Down items in Waterfall button menu.

Snapping to Other Objects

When you drag an object or change its size, MagicPlot will try to snap the bounds of this object to other objects. While snapping MagicPlot shows you a red ruler and an object to which the bounds are snapping. If you do not want to align your objects this way, hold Ctrl key to disable snapping.



See Also

- Scale Scrolling for Data Navigation
- Reading Plot Data, Measuring Distances, Curves Selection

Scale Scrolling for Data Navigation

MagicPlot provides useful plot data navigation (scale scrolling and zooming). Here are several tools and methods:

- Mouse wheel rotation inside the current Axes box scrolls x/y or zooms x/y scale. Ctrl and Shift keys toggle the mode
- Scale box zoom tool
- Hand tool (only if the image zoom is 1x, otherwise the while image will be scrolled in window)
- Right mouse button dragging always works as Hand tool (except Mac OS X)
- The scrollbars (only if the image zoom is 1x, otherwise the while image will be scrolled in window)
- Scale buttons on the toolbar.




Do not Confuse Scale Scrolling and Image Zoom

- **Scale scrolling** affects the x/y scale minimum and maximum values. Use scale scrolling for data navigation
- **Image zoom** enlarges the entire image. Use image zoom for accurate drawing of small objects.

Current Axes

If your Figure contains more than one Axes box, MagicPlot indicates which Axes are currently selected with blue circle sectors in the corners of Axes box. The current Axes selection affects the action of scale buttons and Add to Selected Axes item in Table context menu. It also helps you to distinguish the Axes when you change style in the Figure Properties dialog window.



See Also


- Drawing on Figures and Fit Plots, Image Zoom and Objects Selection
- Reading Plot Data, Measuring Distances, Curves Selection

Reading Plot Data, Measuring Distances, Curves Selection

MagicPlot shows mouse cursor data coordinates in status line. If you have several axes on one Figure, cursor coordinates relative to selected axes are shown.


Crosshair Cursor

MagicPlot can draw crosshair cursor. To turn it on use View → Crosshair Cursor menu item.




Reading Plot Data

MagicPlot denotes the data point under the mouse cursor with square brackets. The accurate table value in this point along with table name, row and column numbers is shown in status line in the bottom of main window in the following format:



Folder | Table [x column; y column][row] = (x value; y value)

Curve Context Menu




Use context menu of the Curve to open table with data or to open properties dialog.

Measuring Data Distances with Scale Zoom Tool

You can use Scale Zoom tool to measure the distances on plots. MagicPlot shows the distance in

status line when you select zoom box by mouse dragging. You can press Esc or reduce box size to zero before releasing mouse button to prevent zooming if you want only to see the distance. If multiple axes are located under cursor MagicPlot will show the distance in terms of current axes (showed with blue corners).





Selecting Curves in Turn Using Keyboard

Curves on Figures and Fit Plots can be selected with mouse click. You can also select Curves in turn using Arrow keys or Tab/Shift+Tab keys:

- \rightarrow or \downarrow or Tab selects the next Curve
- ← or ↑ or Shift+Tab selects the previous Curve.

If no Curves are selected the first pressing on these keys will select the first Curve. If the Figure contains multiple Axes, the Curves in all Axes are accessible in turn by this method.






• Scale Scrolling for Data Navigation

Shifting Curves on Figure and Creating 2D Waterfall

MagicPlot allows you to set individual x and y shifts for every Curve on Figure. This feature may be used to compare several similar Curves on one Figure.



Specified Curve shifts do not affect your data and are used only for drawing current Figure.

Curve shifts can be set in X Shift and Y Shift columns in Axes Components table (scroll table right if these columns are not visible). Waterfall menu contains items for making and resetting 2D waterfall and reversing curves order.

- Reset Shifts sets all x and y shifts to zero
- Make Waterfall automatically calculates shifts and arranges Curves

Make Waterfall menu item opens waterfall window in which you can specify shift increment. MagicPlot tries to guess handsome shift values on the basis of number of curves and current scale.


Make Wa	terfall
?	Specify shift per one curve: Shift X 20 Shift Y 2
	OK Cancel

See Also

- Creating a Figure
- Adding and Arranging Axes Boxes on a Figure
- Adding and Arranging Curves on Figure Axes
- Specifying Axis Multiplier, Prefix and Suffix
- Using Figure Templates

Colours and Opacity Adjustment

In MagicPlot you can set the opacity of each object (curve, text label, rectangle, etc.) to make it semitransparent. Opacity is treated as a property of object color. You can set opacity in Opacity submenu in color pop-up menu which opens by clicking on color button. Opacity percentage is shown on colour button.




• Creating Transparent Figures and Fit Plots

Creating Transparent Figures and Fit Plots

To create an image with transparent background open Figure Properties or Fit Plot Properties dialog window and set Transparent Background radio button in Canvas tab.

The background of transparent Figures and Fit Plots is shown with a grey-and-white chequerboard. If you are preparing a picture for a dark background you can change the colour of chequerboard to dark grey by selecting View \rightarrow Transparency Checkerboard in main menu.

In case of transparent background you can set the preview background colour in Image Preview window.



• Colours and Opacity Adjustment

Using of Dimensions Toolbar

This toolbar is intended for precise setting of the position and size of one or more selected drawn objects on Figure or Fit Plot.

You can open Drawing Dimensions toolbar by selecting Tools \rightarrow Drawing Dimensions in main menu. Dimensions toolbar may be left opened.

L Dime	ensions 💌
X:	20.0272
Y:	0.5621
Width:	3.0507
Height:	3.2424
Units:	[cm] -

Drawing Dimensions toolbar shows the coordinates and size of currently selected object(s). You can also specify the coordinates or size of several components.

- The x value is measured from the left edge of the canvas.
- The y value is measured from the top edge of the canvas.
- For rectangle or ellipse the specified coordinates determine the position of the upper-left corner.
- For text label:
 - x determines the left edge, center or right edge of text according to text alignment of label.
 - $\circ\,$ y determines the baseline position of the first line.

• For line or arrow the specified coordinates determine the position of the beginning.

Inserting Special Symbols and Greek Letters

MagicPlot supports any WUnicode symbols, including Greek letters and many special symbols.

The help on inserting Greek letters and special symbols is also available in Help menu.

Typing Greek letters with Keyboard Shortcuts

To insert Greek letter type Ctrl+G (Command G on Mac OS) and then type Latin letter mentioned in the table below.

Greek Letter Name Greek Symbol		On Keyboard (Ctrl+G, then)	
Alpha	Αα	A a	
Beta	Ββ	B b	
Gamma	Γγ	G g	
Delta	Δδ	D d	
Epsilon	Eε	Еe	
Zeta	Zζ	Zz	
Eta	Нη	Ηh	
Theta	Θθ	Qq	
Theta (alt.)	θ	J	
lota	lι	li	
Карра	Кк	K k	
Lambda	Λλ	LI	
Mu	Μμ	M m	
Nu	Νv	Nn	
Xi	Ξξ	Хх	
Omicron	0 0	0 o	
Pi	Ππ	Рр	
Rho	Ρρ	Rr	
Sigma	Σσ	S s	
Tau	Ττ	Τt	
Upsilon	Υυ	Uu	
Phi	Φφ	Ff	
Phi (alt.)	ф	j	
Chi	Хχ	Сс	
Psi	Ψψ	Υу	
Omega	Ωω	W w	

Inserting Math Symbols with Keyboard Shortcuts

To insert math symbol type Ctrl+M (Command M on Mac OS) and then type symbol mentioned in the

table below.

Symbol name	Symbol	On Keyboard (Ctrl+M, then)
Multiplication sign	×	* or x
Middle dot (multiplication)		. (dot)
Division slash	/	/
Minus sign	-	-
Plus-minus sign	±	+
Minus-plus sign	Ŧ	=
Not equal	≠	n
Infinity	∞	8

To see the full list of shortcuts select Help \rightarrow Insert Greek Letters and Math menu item.

Inserting Special Characters by Character Sequences


To insert the following special characters, simply type character sequences, as shown in the table below. Character sequences will be replaced with special characters when you exit the edit mode (but only if selected font contains required symbols).

You can disable auto	replacing	in Typography	tab of MagicPlot Prefere	ences.

Symbol name	Symbol	Char sequence
Em dash	—	
En dash	-	
Ellipsis		
Much less than	«	<<
Much greater than	≫	>>
Less than or equal to	≤	<=
Greater than or equal to	≥	>=
Plus-minus sign	±	+/-
Minus-plus sign	Ŧ	-/+

Unicode Code Point Finding out

MagicPlot shows in status bar the WUnicode Wcode point of character highlighted in text label. To view code point select exactly one character in text label in Figure of Fit Plot.



• Advanced Typography Features


Advanced Typography Features

MagicPlot provides accurate typography in text labels and axes labels. You may toggle some features in 'Typography' tab of MagicPlot Preferences.

🚯 MagicPlot Pre	eferences
Numeric Format Typography Axes Drawing Fitting	Figures and Plots Typography Tilt angle of oblique font, degrees (default is 18°):

Ligatures Support

MagicPlot supports Latin Wligatures in text labels. If you type 'fi', 'fl', etc., those symbols will be shown with ligature glyphs when you exit edit mode.



MagicPlot supports at least the following ligatures:

- fi,fl
- ff, ffi, ffl


Not all fonts contain ligature glyphs. MagicPlot displays ligatures only if the glyphs are included in used font. You can turn the ligatures off in MagicPlot preferences.

The numbers in Wscientific notation need two special characters if you want the typography to be accurate: minus sign and multiplication sign. Many graphing software applications which use simplified typography use letter 'x' and Whyphen-minus (-) in numbers instead of typographically correct special characters. This simplified typography was mainly used in old applications which do not support WUnicode.

MagicPlot can use either correct symbols (default) or simplified. You can change this option in MagicPlot Preferences.

Minus Sign

Various minus-like characters are used in different cases and have different height and length. The height and length of minus sign are equal to those of plus sign and correspond to the size of digits in the font. Here is a comparison of these characters:



When you edit some text, keyboard minus key enters hyphen-minus character. The correct minus character can be typed in text label by pressing Ctrl+M, -, see Inserting Special Symbols for details.

Multiplication Sign

In different languages, multiplication signs differ. In most cases you have to use either '.' or '×' sign. You also can specify any special character or character sequence, for example enter spaces before and after multiplication signs.

1.4×10^{-6}	WMultiplication sign Correct Wminus sign
$1.4 \cdot 10^{-6}$	WMiddle dot Correct minus sign
1.4x10 ⁻⁶	Simplified typography: Latin letter 'x' Whyphen-minus instead of minus

See Also

• Inserting Special Symbols and Greek Letters

Point, pt (unit of measure)

In Wtypography, a Wpoint is the smallest unit of width or height measure. It is commonly abbreviated as pt.

The Wdesktop publishing point (DTP point) is defined as 1/72 inch, it is approximately 0.0139 inch or 0.353 mm. Twelve points make up a pica, and six picas make an inch.

In MagicPlot points are used to set up font size and line widths.

Image Export

To export Figure or Fit Plot image click on Project → Export Image menu item or use corresponding toolbar button. You can set various options of file export format by clicking on Format Options button in Export Image dialog window.

You can also copy image to clipboard.

Raster Image Formats

The following lossless Wraster graphics formats are supported:


- WPNG the most suitable format for Fit Plots and Figures
- WGIF supports only 256 colours and no transparency, out-of-date format
- WBMP uncompressed raster format (large file size)

Setting the resolution of exported raster image

Image resolution for raster export can be set individually for every Figure and Fit Plot in Canvas tab of the Properties window. The default resolution is 300 DPI.

Why is MagicPlot not capable to export images in JPEG format?

WJPEG is a commonly used format of Wlossy compression for photographic images. The JPEG compression algorithm is at its best on photographs and paintings of realistic scenes with smooth variations of tone and color. However, JPEG is not suited for line drawings and other textual or iconic graphics, where sharp contrasts between adjacent pixels cause noticeable artefacts. Such images are better saved in a lossless raster graphics format such as BMP, GIF, PNG or vector graphics formats.



Vector Image Formats

The following Wvector graphics formats are supported:

- WPDF
- WEPS
- WSVG most suitable for web publications
- WEMF the most suitable format for inserting in Windows applications like Microsoft Office

Export in vector graphics formats by virtual printer

You also can use third-party virtual printer software to save an image in vector graphics format (use Project \rightarrow Print menu item).

Image Format Restrictions

- BMP:
 - Transparent background is not supported.
- GIF:
 - Transparent background is supported but semi-transparency is not. Only 256 colours.
- EMF and vector copy on Windows:
 - $\circ\,$ No semi-transparent colors (but transparent background is supported).
 - Image may be opened without antialiasing in some applications.
 - Text tracking changing is not supported
- EPS:
 - Transparency is available only in Acrobat Distiller. Set Allow Pdfmark Transparency checkbox in EPS format options, add /AllowTransparency true into Acrobat Distiller's .joboptions file.
 - $\circ\,$ Transparent images inserted on plots will have solid color background.
- Raster image copying:
 - $\circ\,$ Transparent background is not supported.

See Also

- Copying Images to Clipboard
- Preview Image


Preview Image

Use Project \rightarrow Image Preview menu item to open image preview window. You can also use the Preview button of the toolbar or Ctrl+Shift+P keyboard shortcut (Cmd+Shift+P on Mac).

Preview Features

In preview mode you can:

- Preview in gray scale
- Transparent images can be previewed on selected background color
- Change the zoom of the image



Preview Zoom Options

There are several options for the size of preview:

- Percent of real size. Note: The size will be actually real only if the dots per inch (DPI) is correctly set in your operating system
- Fit to Window, Fit Width, Fit Height fits the size of previewed image to window dimensions
- Pixel-to-Pixel allows you to see the accurate image that you will get using export in raster image format. The resolution of exported raster image is evaluated as a product of canvas size and DPI value specified in Canvas tab of Figure/Fit Plot Properties window.

Copying Images to Clipboard

When you edit a presentation or report, it is very useful to paste images from MagicPlot to another application directly through clipboard without saving them.

MagicPlot supports copying images to clipboard in both **raster** and **vector** formats from Edit menu. Transferring vector images is always preferable because these images are scaled more precisely. However, we have found that some applications do not support pasting vector images, or paste vector images with distorted text. In this case, please use copying raster image.

See Also


• Image Export

MagicPlot Calculator

MagicPlot Calculator is a useful formula calculator built in MagicPlot. To open calculator use Tools \rightarrow Calculator menu item.

Using calculator outside MagicPlot

Calculator window stays on top when MagicPlot main window is minimized to task bar (Dock on Mac), so you can use the Calculator when working with other applications.



Using the Calculator

- Type expression like (12+4)*sin(pi/2) and press Enter to get the result
- Type a=5 to set variable a to 5
- Use Up/Down keys to recall previously entered expressions
- Use ans variable or press Ctrl+Up to insert the result of latest operation
- Standard functions and variables (sin, cos, pi, e, etc.) are supported

MagicPlot Calculator uses the same Expression Syntax as other formula fields in MagicPlot application.

See Also

• Expression Syntax

Keyboard Shortcuts

MagicPlot keyboard shortcuts are almost the same in different operating systems (Windows, Mac OS, UNIX-like). The main difference is in modifier keys used: Ctrl on PC (Windows, UNIX-like) and Command on Mac. Some shortcuts were altered to avoid coincidences with system ones.

You can find these keyboard shortcuts in MagicPlot by selecting Help \rightarrow Keyboard Shortcuts menu item.

Mac Keyboard Symbols

- X Command (Meta) key
- 1 Shift key
- 🕆 Option (Alt) key
- ^ Control key

Common Shortcuts

Windows and UNIX-like Key	Mac OS Key	Action	
Ctrl+O	жΟ	Open project	
Ctrl+S	жs	Save project	
Ctrl+Shift+S	光 î S	Save project as	
Ctrl+N	ЖN	New project	
Ctrl+Shift+N	¥îN	New table	
Ctrl+I	жI	Import table from text file	
Ctrl+Shift+I	₩ î 	Import table from clipboard	
Ctrl+P	ЖР	Print (image or table)	
Ctrl+Shift+P	፝ የ	Preview image	
Ctrl+E	ЖЕ	Export image or table	
Ctrl+K	жĸ	Open calculator	
Ctrl+U	жU	MagicPlot preferences	
Ctrl+Q	жQ	Quit	
	Undo/Redo		
Ctrl+Z	жz	Undo	
Ctrl+Shift+Z or Ctrl+Y	ቼ î Z or ቼ Y	Redo	
Ctrl+Shift+H	፝ 	Show command history window	
Clipboard			
Ctrl+X	жх	Cut	
Ctrl+C	жC	Сору	
Ctrl+V	жv	Paste	
Ctrl+A	Ж A	Select all	

Table Shortcuts

Windows and UNIX-like Key	Mac OS Key	Action
F2 or Double click	Double click	Edit cell

Windows and UNIX-like Key	Mac OS Key	Action
Ctrl+F2		Set or edit column formula
F4	F4	Rename column (edit header)
Ctrl+Enter	ដ Return	Recalculate column
Alt+Drag header (Win/Meta+Drag header on UNIX)	∽ Drag header	Rearrange table columns

Figure and Fit Plot Shortcuts

Windows and UNIX-like Ke	ey Mac OS Key	Action
Alt+Enter	¬⊂ Return	Open Figure or Fit Plot properties window
Arrows keys	Arrows keys	Move selected object(s) by 1 mm
Shift+Arrows keys	1 Arrows keys	Move selected object(s) by 0.1 mm
Escape	Escape	Clear selection
Delete or Backspace	Delete or Backspace	Delete selected objects
F2 or Double click	F2 or Double click	Edit selected text label
Moving and Resizing Drav	vings	
Ctrl+Drag object	ж Drag object	Disable rulers and snapping to other objects
Shift+Drag corners	û Drag corners	For rectangle and ellipse: preserve aspect ratio For line and arrow: disable snapping to 0°, 45°, 90°
Alt+Drag corners	∽ Drag corners	For rectangle and ellipse: stretch relative to center
Text Labels Editing ²⁾	:	
Ctrl+Enter or Shift+Enter	೫ Return or î Return	Apply changes
Escape	Escape	Apply changes
Enter	Return	New line
Ctrl+G, then letter	ቼ G, then letter	Type Greek letter (letters correspondence)
Ctrl+M, then symbol	ቼ M, then symbol	Type special math symbol (symbol list)
Ctrl+B	жв	Bold
Ctrl+I	жI	Italic
Ctrl+O	жо	Oblique
Ctrl+U	жU	Underlined
Ctrl+L	ℋ L	Align left
Ctrl+E	жE	Center
Ctrl+R	ж R	Align right
Ctrl+J	жJ	Justify
Ctrl+-	ж –	Subscript
Ctrl++	ж +	Superscript
Scale Range Scrolling and	Zoom	
Scrolling ³⁾	Scrolling	Vertical (Y) scale scrolling
Shift+Scrolling	Scrolling or Horizontal scrolling	Horizontal (X) scale scrolling
Ctrl+Scrolling	Ж Scrolling	Vertical (Y) scale zooming
Ctrl+Shift+Scrolling	第 ↑ Scrolling or ೫ Horizontal scrolling	Horizontal (X) scale zooming

Windows and UNIX-like Key	Mac OS Key	Action		
Left mouse button+Scrolling	^ Scrolling	Proportional (X and Y) scale zooming		
Image Zoom				
Ctrl++	ж +	Zoom in		
Ctrl+- or Alt+Click	೫ – or ⁻∠ Click	Zoom out		
Ctrl+* or Ctrl+0	ස * or	Full view		
1)	1	•		

If you use Opera browser with Opera Turbo option the images will appear recompressed in JPEG format and this comparison is void.

These shortcuts are activated in text label edit mode.

3)

Scrolling here means mouse wheel rotation or touchpad vertical scrolling.

From: https://magicplot.com/wiki/ - MagicPlot Manual

Permanent link: https://magicplot.com/wiki/manual?rev=1288088831

Last update: Sun Nov 8 12:20:32 2015

